



Protocols for Assessing Transformation Rates of Nitrous Oxide in the Water Column

Annie Bourbonnais^{1††}, Claudia Frey^{2†}, Xin Sun^{3,4}, Laura A. Bristow⁵, Amal Jayakumar³, Nathaniel E. Ostrom⁶, Karen L. Casciotti⁷ and Bess B. Ward³

¹ School of the Earth, Ocean and Environment, University of South Carolina, Columbia, SC, United States, ² Department of Environmental Sciences, University of Basel, Basel, Switzerland, ³ Department of Geosciences, Princeton University, Princeton, NJ, United States, ⁴ Department of Ecology and Evolutionary Biology, Yale University, New Haven, CT, United States, ⁵ Nordsee, Department of Biology, University of Southern Denmark, Odense, Denmark, ⁶ Department of Integrative Biology, Great Lakes Bioenergy Research Center, Michigan State University, East Lansing, MI, United States, ⁷ Department of Earth System Science, Stanford University, Stanford, CA, United States

OPEN ACCESS

Edited by:

Johannes Karstensen,
GEOMAR Helmholtz Center for Ocean
Research Kiel, Germany

Reviewed by:

Annette Kock,
GEOMAR Helmholtz Center for Ocean
Research Kiel, Germany
Jana Milucka,
Max Planck Institute for Marine
Microbiology (MPG), Germany

*Correspondence:

Annie Bourbonnais
abourbonnais@seo.sc.edu

[†] These authors have contributed
equally to this work

Specialty section:

This article was submitted to
Ocean Observation,
a section of the journal
Frontiers in Marine Science

Received: 29 September 2020

Accepted: 05 March 2021

Published: 22 April 2021

Citation:

Bourbonnais A, Frey C, Sun X,
Bristow LA, Jayakumar A,
Ostrom NE, Casciotti KL and
Ward BB (2021) Protocols
for Assessing Transformation Rates
of Nitrous Oxide in the Water Column.
Front. Mar. Sci. 8:611937.
doi: 10.3389/fmars.2021.611937

Nitrous oxide (N₂O) is a potent greenhouse gas and an ozone destroying substance. Yet, clear step-by-step protocols to measure N₂O transformation rates in freshwater and marine environments are still lacking, challenging inter-comparability efforts. Here we present detailed protocols currently used by leading experts in the field to measure water-column N₂O production and consumption rates in both marine and other aquatic environments. We present example ¹⁵N-tracer incubation experiments in marine environments as well as templates to calculate both N₂O production and consumption rates. We discuss important considerations and recommendations regarding (1) precautions to prevent oxygen (O₂) contamination during low-oxygen and anoxic incubations, (2) preferred bottles and stoppers, (3) procedures for ¹⁵N-tracer addition, and (4) the choice of a fixative. We finally discuss data reporting and archiving. We expect these protocols will make ¹⁵N-labeled N₂O transformation rate measurements more accessible to the wider community and facilitate future inter-comparison between different laboratories.

Keywords: nitrous oxide, ¹⁵N-tracer incubations, production, consumption, rates, water-column, greenhouse gas

INTRODUCTION

Nitrous oxide (N₂O) is a greenhouse gas with a 300 times higher warming potential than carbon dioxide (Myhre et al., 2013) as well as the dominant stratospheric ozone-depleting substance (Nevison and Holland, 1997; Ravishankara et al., 2009). One third of global natural N₂O emissions to the atmosphere are from marine environments, yet N₂O production and consumption in productive coastal waters are still not well quantified (e.g., Nevison et al., 2004). It is also unclear how N₂O cycling will respond to ongoing expansion of marine oxygen (O₂) deficient zones (Stramma et al., 2008) and climate change.

N₂O production rates are estimated by tracking the transformation of a ¹⁵N-labeled substrate (¹⁵N-NH₄⁺, ¹⁵N-NO₂⁻, or ¹⁵N-NO₃⁻) to the N₂O product. N₂O is produced by aerobic nitrification [by either hydroxylamine oxidation, nitrifier-denitrification or a hybrid mechanism (Trimmer et al., 2016; Stein, 2019)] or denitrification under low-O₂ conditions. N₂O

consumption rates are estimated by tracking the transformation of ^{15}N -labeled N_2O to the N_2 product under anaerobic conditions (Figure 1). N_2O production during water-column denitrification is mostly performed by prokaryotic microbes (Prosser et al., 2020). However, eukaryotes (such as fungi, protists, benthic foraminifera, and gromids) also contribute to N_2O production in sediments and soils (Piña-Ochoa et al., 2010; Huang et al., 2017), but their roles in water-column processes remains to be confirmed. Fungi have been specifically proposed to be involved in the generation of hybrid N_2O (Shoun et al., 2012).

Despite the urgent need to better constrain N_2O transformations in both marine and freshwater systems, clear step-by-step protocols are lacking. This issue was recently raised during the “Oceanic Methane and Nitrous Oxide Workshop: The present situation and future scenarios!” at Lake Arrowhead in October 2018 (Wilson et al., 2020), motivating the writing of standard operating procedures that would facilitate future inter-comparison efforts between different laboratories.

The Lake Arrowhead workshop was instrumental in connecting us with people with relevant expertise in the field. Researchers with relevant expertise were contacted and invited to contribute to this manuscript. We also reviewed current literature using ^{15}N -labeled compounds to measure N_2O production and consumption rates to get an overview of existing techniques. As part of this process, we realized that the methodologies used are influenced by several factors, such as specific research questions, studied ecosystems, or available analytical equipment. Hence, we concluded that there is not one “best method,” but several acceptable methods, with generally only slight procedural differences. Finally, we present techniques used by six laboratories working in freshwater and marine environments (Michigan State University, Princeton University, Stanford University, University of Basel, University of South Carolina and University of

Southern Denmark). A draft of this manuscript was also disseminated to the broader scientific community before publication, including experts who could not attend the Lake Arrowhead workshop. Our goal is to provide detailed and community-reviewed protocols to measure water-column N_2O production and consumption rates using ^{15}N -tracer incubations in marine and freshwater environments. This synthesis is indispensable for new researchers trying to reproduce these experiments but also represents the first step toward a thorough inter-comparison of these protocols between labs.

MATERIALS AND METHODS

The following section will explain the workflow protocols for N_2O production (Part A) and N_2O consumption (Part B) in detail. Part B is further divided into methods #1 and #2.

Part A: N_2O Production During Aerobic Nitrification and Denitrification

Different treatments are used to measure N_2O production during aerobic nitrification (Table 1 and Figures 1, 2). Figure 3 shows the workflow for ^{15}N - NH_4^+ incubation experiments, which could be done with or without a headspace. The same workflow would apply for ^{15}N - NO_2^- incubations and experiments targeting denitrification (^{15}N - NO_3^-). Adding a headspace is strongly recommended if O_2 concentrations are to be manipulated during the incubations, by either purging the liquid phase with inert gas to remove remnant O_2 or by adding O_2 (Ji et al., 2015; Frame et al., 2017) via additions of air saturated *in situ* seawater, air or pure O_2 gas. Different O_2 treatments should be implemented immediately after creating a headspace. It is also practical to add a headspace if samples are degassed directly from the bottle during Isotope Ratio Mass Spectrometer (IRMS) analysis (e.g., Ji et al., 2015). If O_2 manipulations or anoxic experiments are performed (Figure 3A), purging the liquid phase (to remove O_2) will also remove *in situ* N_2O . Thus the addition of N_2O at natural abundance is highly recommended to increase N_2O concentrations above the detection limit of GC-IRMS (typically 1–5 nmol). However, no headspace is necessary if the O_2 concentrations are not manipulated for the different treatments and if seawater is first transferred from the bottle to an extractor and then degassed before purge and trap and IRMS analysis following the protocols by McIlvin and Casciotti (2010) or Bourbonnais et al. (2017).





TABLE 1 | Different ^{15}N -labeled substrate additions to measure N_2O production during aerobic nitrification and denitrification.

Process	Treatment
Hydroxylamine oxidation	^{15}N - NH_4^+
Nitrifier-denitrification	^{15}N - NO_2^-
Hybrid	^{15}N - $\text{NH}_4^+ + ^{14}\text{N}$ - NO_2^- or ^{15}N - $\text{NO}_2^- + ^{14}\text{N}$ - NH_4^+
Denitrification	^{15}N - NO_2^- or ^{15}N - NO_3^-



Supplies

Note: Items that can be substituted by other brands are marked with a *.

Chemicals/Gases

- ^{15}N tracer (>98%): NH_4Cl (98.5% ^{15}N), NaNO_2 (99.2% ^{15}N), and NaNO_3 (98.5% ^{15}N) salts* (NLM-467, NLM-658, and NLM-157, Cambridge Isotope Laboratories)
- Non-labeled NH_4Cl and NaNO_2 salts
- Solutions of saturated HgCl_2 or 50% w/v ZnCl_2

- He and N_2 tanks (UHP 5.0 to 4.6 grade) for purging the liquid phase
- 1,000 ppm N_2O gas at natural abundance (add only if purging the liquid phase – see section “Purging the Liquid Phase With He or N_2 Gas”)
- O_2 (UHP, 4.4 grade) gas for O_2 manipulation experiments

Other Supplies


- Serum glass bottles (60–125 mL) with a 20 mm opening diameter [Wheaton #223746 (60 mL) or #223748 (125 mL)]*
- Note: The volume of the bottles reported by the vendor differs from the actual volume as it does not include the neck of the bottle. For instance, the measured volume for the 125 mL bottles is about 160 mL.

- 1 M HCl acid bath
- MilliQ water supply
- Muffle furnace
- Disposable gloves
- Plastic volumetric flasks, pipettes and pipette tips to prepare ^{15}N -tracer solution at sea

- Glass beads (about 1 mm diameter)

Note: These are only needed for headspace-free incubations.

- Tygon tubing (approximately 1 m length) with adaptors to fit the Niskin bottle opening
- Gray butyl septa (20 mm) (Wheaton #20-0025)
- Aluminum crimp seals (20 mm) (Wheaton #224178-01)
- Crimper for 20 mm cap
- Decrimper for 20 mm caps



- Plastic container to hold bottles during sampling
- Various size luer-lock gas tight glass syringes for liquid tracer addition* (e.g., 1 mL Hamilton gastight syringe model 1001 TLL, #81320; 100 μ L gastight syringe model 1710 TLL, #81020) with a 25G or 23G regular bevel needle
- Non-gas-tight syringes*, e.g., BD luer-lock tip 1 mL (#309628), 3 mL (#309657), 5 mL (#309646), 10 mL (#309604), and 50 mL (#309653)
- Various size needles*: BD PrecisionGlide Regular Bevel needles, e.g., 25G $\times$ 5/8" (#305122) or 23G $\times$ 3/4" (BD #305143) and 25G $\times$ 1 1/2" (#305127) or 23G $\times$ 1 1/4" (BD #305120) to inject isotopic tracers and HgCl₂
- 18G, 6" stainless steel needle* (that reaches the bottom of the bottle) for purging the liquid phase (e.g., Cadence science #9860) or 21G $\times$ 4 3/4" (B Braun #4665643) (depending on bottle size)
- Purging rack with Viton tubing* (e.g., 1/16" ID $\times$ 1/8" OD, Fisher Scientific, #NC0511742) and Swagelok unions for purging liquid phase
- Dual stage regulators, stainless steel or brass tubing, Swagelok fittings, and mechanical flow controller (e.g., Porter, VCD-1000) for purging and gas transfer
- Fixed needle gastight glass syringes to inject gases*: i.e., Hamilton, sample lock: 1 mL (#81356), 500 μ L (#81256), 250 μ L (#81156), and 100 μ L (#81056)
- Incubator (or temperature-controlled room or container) covering the *in situ* temperature range of the samples
- O₂ probe/meter and oxygen sensor spots (Oxysense, Pyroscience, or custom-made sensor spots as in Larsen et al., 2016) for O₂ monitoring during incubations
- 25 mm polycarbonate (Whatman nucleopore, 0.45 μ m) or GF/F (Whatman, 0.7 μ m) filters* (e.g., Fisher Scientific #09-874-64)
- Acid-washed syringe filter holder for filtration* (e.g., Pall pressure syringe filter holder: #246800, Hach)
- Acid washed 15–50 mL Falcon conical tubes or high density polyethylene (HDPE) bottles to store filtered aliquots for nutrient and isotope analysis
- IRMS adapted for N₂O isotope measurements (see McIlvin and Casciotti, 2010)
- colored tape and Sharpies for sample labeling
- Notebook, log sheets, and pens

Preparation Before the Sampling Expedition

Acid Wash All Glassware.

Prepare ¹⁵N Tracer and Non-labeled Salts. Pre-weigh ¹⁵N tracer and non-labeled salts and store in acid washed small glass vials with screw caps. Label properly. Fresh solution will be prepared in the field.

Build Purging Rack. We recommend building a purging rack using Viton tubing and Swagelok unions, similar to the racks shown in part B, method #2 below.

Degas the Butyl Stoppers and Caps. Stoppers are degassed by boiling them in purified water for 5 min and stored under vacuum or He (see De Brabandere et al., 2012).

Transfer Natural Abundance N₂O and O₂ Gases. It is strongly recommended to transfer N₂O and O₂ gases in to several 20 mL glass vials capped with butyl septa and aluminum crimp seals to avoid unnecessarily shipping gas tanks to research vessels. This should be done just before shipping materials to the ship.

Sample Collection

Wheaton glass serum bottles should be acid-washed, rinsed with MilliQ water, and heated for at least 4 h at 500°C before sample collection, to remove any organic material. Note that bottle size varies among protocols, ranging from 60 mL (Ji et al., 2015) to 160 mL (Frame et al., 2017; **Figure 4A**). The ideal bottle size should be selected based on the N₂O detection limit of the IRMS to be used for analysis.

Sample collection is done using the same procedure as for N₂O concentrations (see Wilson et al. (2018) for more detail). Briefly, each 160 mL glass serum bottle is filled from a Niskin bottle or pump profiling system using Tygon tubing, which is inserted all the way to the bottom of the bottle and allowed to overflow the bottle volume several times. The flow from the Niskin bottle must be reduced while filling the bottles to avoid splashing. After filling, the bottle is capped, bubble-free, with a gray butyl stopper and aluminum seal.

For headspace-free incubations, a small glass bead (1 mm diameter) is added to the glass serum bottles before sampling as it facilitates mixing of the tracer at the start and preservative at the end of the incubations.

For measurement of N₂O production *via* aerobic nitrification, some protocols call for sampling water from the Niskin bottles directly into bigger containers if O₂ contamination is not an issue (e.g., 3–10 L LDPE or HDPE containers; Frame et al., 2017). Subsampling is then done into glass serum bottles after ¹⁵N-tracer addition. This method has the advantage of homogenizing the seawater as well as the added ¹⁵N tracer for each treatment, thus decreasing the standard deviation of replicate measurements. The disadvantage is, that this procedure introduces O₂ into the samples and should not be used in low-O₂ environments.

Since seawater samples are not filtered, some particles may be contained within incubation bottles. However, it is unclear from studies conducted to date if particle associated activity is adequately accounted for during the incubations (Ganesh et al., 2014; Fuchsman et al., 2017).

Sufficient numbers of bottles should be filled at each station and depth to enable at least duplicate measurements of each treatment and time point (see section "Incubation" below).

Record metadata, such as Niskin bottle sampled, depth, location, as well as a few basic data (salinity, temperature, time bottle closed) in order to be able to directly link these samples to databases of hydrographic data from the sampling expedition in repositories such as BCO-DMO (Biological and Chemical Oceanography Data Management Office). In addition to metadata, samples should be collected from all incubation depths for measurements of relevant geochemical (and microbiological) parameters of the sampled water (see section "Data Reporting and Archiving").




FIGURE 4 | Headspace-free filled 160 and 60 mL glass serum bottles **(A)**, creating a headspace with a low He flow (up to 10 mL/min) **(B)**, and 20 mL headspace in 160 mL serum bottles (12.5% headspace) and 5 mL headspace in 60 mL serum bottles (8% headspace) **(C)**.

Headspace Introduction

If O_2 concentrations need to be controlled during treatments, a He or N_2 headspace (5–25% of the bottle volume) is created (**Figures 4B,C**), e.g., 3–10 mL for 60 mL bottles (Ji et al., 2015) or 10–40 mL for 160 mL bottles (Frame et al., 2017). However, in fully oxygenated waters a He headspace can lead to a drawdown of O_2 due to diffusion from the liquid into the headspace. Hence, in oxygenated waters an air headspace is preferable. The headspace is added by either flushing a 5 mL or 60 mL syringe several times with He before injecting the desired amount of He or N_2 in the bottles using a $23G \times 1\frac{1}{2}''$ needle and a vent needle ($23G \times 3/4''$) or by directly adding He or N_2 gas with a low flow (up to 10 mL/min) using a long needle ($23G \times 1\frac{1}{2}''$) attached to a 10 or 50 mL syringe as the outlet (**Figure 4B**).

Purging the Liquid Phase With He or N_2 Gas

For incubations of anoxic waters or O_2 manipulation experiments, purging the liquid phase with He or N_2 gas prior to incubations is strongly recommended. *In situ* N_2O is also completely removed during this process if the volume of the serum bottles or exetainers is exchanged 100-times (Frey et al., 2020). In most systems, N_2O production rates are not high enough to produce sufficient N_2O over a 24-h incubation to be above detection limit of GC-IRMS analysis (typically 1–5 nmol). N_2O consumption could further reduce N_2O concentrations in incubations of anoxic waters. If samples are purged, a non-labeled (i.e., at natural abundance) N_2O carrier

gas should be added back into the serum bottles to (1) lower the ^{15}N enrichment to be within the range that can be measured by the mass spectrometer and (2) to assure sufficient quantities of N_2O for analysis on the IRMS.

For incubations of anoxic waters or O_2 manipulation experiments, it is highly preferable to purge the liquid phase to remove O_2 introduced during sampling. For anoxic incubations, 60 mL bottles are purged with a He flow of 0.4 L/min for 15 min, exchanging the volume 100-times. 160 mL serum bottles should be purged for 30 min at a He flow of 0.6 L/min. If a different flow or bottle size is used, the length of purging the liquid phase should be tested with an O_2 optode and should be adjusted accordingly. For anoxic incubations, O_2 should be removed as O_2 in the nanomolar range has been shown to influence N_2O production and consumption rates (Dalsgaard et al., 2014). Inflow needle should reach to the bottom of the serum bottle, vent needle only needs to reach into the headspace. Although not always possible, it is preferable to do all these manipulations under *in situ* conditions i.e., *in situ* temperature, and under red light (if the samples were collected from below the euphotic zone).

Add natural abundance N_2O to the samples. The amount of natural abundance N_2O added should be calculated based on detection limit of the IRMS. The amount of N_2O will thus need to be adjusted for bigger bottles (or smaller exetainers) and also depends on headspace volume. For instance, 100 μL of 1,000 ppm N_2O (in He) for a final concentration of 20 nmol/L N_2O in the

liquid phase is added in 60 mL serum bottles [57 mL liquid and 3 mL headspace, based on equilibrium concentration calculated using the Weiss and Price (1980) solubility equation]. A 0.5 mL fixed needle glass syringe with a 23G regular bevel needle is flushed two times with the 1,000 ppm N_2O (in He) and then 100 μL of the gas is added into the liquid phase of the sample. Confirmation that the gas is successfully injected, and the needle is not clogged, can be obtained by visual observation of bubbling. Shake the bottle to obtain homogenization.

¹⁵N-Tracer Addition

The ¹⁵N tracer should be degassed with He or N_2 gas before being added directly to glass serum bottles. Tracer is added to each incubation bottle using a glass gas tight syringe (50 μL to 1 mL) flushed several times with He. A small needle gauge (e.g., 25G or 23G $\times$ 1 1/2") is preferred to preserve septa integrity. A vent needle (23 G $\times$ 3/4") attached to a 5 mL syringe (plunger removed) filled with seawater is used during tracer addition if incubated without a headspace. It is preferable to use a vent needle even for small volume additions of tracer (<100 μL) to ensure reproducible tracer additions. The needle used for ¹⁵N-tracer additions should be longer than the vent needle such that the added tracer is not lost through the vent. Shake the bottle to obtain homogenization.

At least one bottle per treatment should be immediately sacrificed upon addition of the tracer for each treatment to correct for abiotic labeled N_2O production ($T = 0$), if any, due to preservative addition and storage (e.g., see Ostrom et al., 2016). This sample is also important for determining the fraction of ¹⁵N-labeled substrate at the start of the experiment.

Incubation

Replicate (preferably triplicate) samples per time point amended with each ¹⁵N-tracer should be incubated at *in situ* temperature and light level using at least three time points for up to a 48 h period. Incubating for more than 48 h is generally not recommended as it is likely to result in significant changes to the microbial community and activity known as "bottle effects" (Garcia-Robledo et al., 2016).

Ideally, the concentration of O_2 in the bottle is monitored over time during the incubation using non-invasive O_2 measurement technology, such as OxySense¹, PyroScience² or custom-made sensors (e.g., see Larsen et al., 2016). A sensor dot is attached inside the bottle prior to filling, to ensure that the sensor dot is located in the liquid phase. After injecting the tracer, the O_2 concentration is measured continuously using a fiber optic pen. This step is especially important during O_2 -sensitive treatments. Separate bottles (at least one per treatment) should be used for O_2 monitoring. The lower detection limit is generally > 60 nmol L^{-1} O_2 for the OxySense and PyroScience sensors but the custom-made trace sensor described in Larsen et al. (2016) measure O_2 concentrations as low as ~ 5 nmol L^{-1} . A lower detection limit (nmol range) is preferable since oxygen at nanomolar levels has been shown to influence denitrification rates (Dalsgaard et al., 2014).

¹<http://www.oxySense.com/>

²<http://www.pyroScience.com/>

Termination and Storage

In order to analyze the production rate of other dissolved nitrogen compounds from the same incubation bottle (i.e., in ¹⁵ NH_4^+ treatments, ¹⁵ NO_2^- production rates can be determined in the same time course bottles as the N_2O production rates), two strategies can be applied. The first one is, that before preserving the sample, 10–40 mL (depending on bottle size) should be withdrawn from at least one bottle per time point for each treatment using a 10 or 50 mL syringe with a 25G needle, filtered using polycarbonate membrane or GF/F filters, and stored at -20°C . The volume removed should be replaced with He or N_2 . The second option is, that no sample is taken prior to fixation and the dissolved fractions are analyzed after the gaseous components are measured. Fixation agents (HgCl_2 , ZnCl_2) do not interfere with NO_x box measurements (see Braman and Hendrix, 1989) nor the denitrifier and azide methods (Sigman et al., 2001; McIlvin and Altabet, 2005; Weigand et al., 2016). Concentration and isotopic composition measurements of dissolved inorganic nitrogen (¹⁵N-labeled NH_4^+ , NO_2^- , and NO_3^-) are needed to assess the labeled fraction of ¹⁵N-tracer substrates used in the calculation of N_2O production rates from each substrate (see calculation templates in the **Supplementary Material**), and can be used to assess ammonium oxidation, nitrite oxidation or nitrate reduction rates in parallel.

Samples are preserved by adding 0.1 mL of five times diluted saturated solution of HgCl_2 or 50% (w/v) ZnCl_2 to each bottle with a 1 mL plastic syringe to arrest microbial activity. Diluting the HgCl_2 saturated solution reduces the toxicity of the hazardous wastes without any impact on sample preservation (e.g., see Bourbonnais et al., 2017; Casciotti et al., 2018). Important considerations: ZnCl_2 should not be used for ¹⁵ NO_2^- incubations because it triggers abiotic N_2O production. It should also be noted that HCl should not be used for N_2O production experiments as N_2O is produced from abiotic NO_2^- reduction under acidic and anoxic conditions (Zhu-Barker et al., 2015).

Preserved samples should be stored in the dark and likely keep for several months although the maximum storage time has not been thoroughly tested. We recommend analyzing these samples as soon as possible.

Preparation of Internal Isotope Standards for IRMS Analysis

Internal isotope standards, to determine the atom fraction of ¹⁵N in NO_2^- or NO_3^- , are prepared by mixing solutions of non-labeled NO_2^- or NO_3^- salts with ¹⁵N-labeled $\text{Na}^{15}\text{NO}_2$ or $\text{Na}^{15}\text{NO}_3$ (>98.5%, Cambridge isotope Laboratories) as described in Frame et al. (2017). The isotopic composition of NO_2^- or NO_3^- is measured by conversion to N_2O using the denitrifier and azide methods (Sigman et al., 2001; McIlvin and Altabet, 2005; Weigand et al., 2016).

Alternatively, ⁴⁶ N_2O gas (Cambridge Isotope Laboratories) and natural abundance N_2O gas can be mixed using a gas tight syringe in different ratios to obtain a range of labeled N_2O standards for calibration. Standards should be made to span the expected range of ¹⁵N enrichment in the samples. These isotope standards are used to verify and/or correct the linearity

of the IRMS and can also be used to calibrate N_2O isotope measurements for the incubation samples.

The accuracy of the internal standards can be assessed by comparing expected (theoretical) with measured values [as in Frame et al. (2017)]. If standard analytical precautions are followed for preparing the dilution series, the deviation from expected vs. measured values should allow correction for any IRMS linearity effects. The precision can be obtained by measuring several replicates for each dilution.

IRMS Analysis

N_2O is analyzed for its concentration and isotopic composition (masses 45/44 and 46/44) using an IRMS with a purge trap system adapted for N_2O measurements (McIlvin and Casciotti, 2010; Ji et al., 2015; Bourbonnais et al., 2017). Briefly, the samples are degassed directly from the bottle (e.g., Ji et al., 2015) or the water is pumped to an online gas extractor where it is completely degassed (McIlvin and Casciotti, 2010) before IRMS analysis. The lower detection limit of most IRMS is typically 1–5 nmol N_2O . It should be noted that a typical IRMS can only analyze samples to a range of about 5% ^{15}N while some instruments are capable of analyzing up to 99% ^{15}N using equal collector resistors (e.g., see Bergsma et al., 2001). Some IRMS have the capability of switching between equal and non-equal resistors to enable analysis of both natural abundance and enriched samples.

Rate Calculations

The equations below describe the calculations using calibrated $\delta^{15}\text{N}_{\text{sample}}$ and $\delta^{18}\text{O}_{\text{sample}}$ values [relative to air (AIR) and Vienna Standard Mean Ocean Water (VSMOW), respectively] to obtain rates of N cycling processes. See Sharp (2017) for example calculations that convert raw sample $\delta^{15}\text{N}$ and $\delta^{18}\text{O}$ values that are expressed relative to an internal reference gas to values expressed relative to AIR and VSMOW using international isotopic reference materials.

Incorporation of tracer during ^{15}N incubations results in an excess of m/z 45 and 46 N_2O :

- (1) Total $^{45}\text{N}_2\text{O} = ^{15}\text{N}^{14}\text{N}^{16}\text{O} + ^{14}\text{N}^{15}\text{N}^{16}\text{O} + ^{14}\text{N}^{14}\text{N}^{17}\text{O}$
- (2) Total $^{46}\text{N}_2\text{O} = ^{15}\text{N}^{15}\text{N}^{16}\text{O} + ^{14}\text{N}^{14}\text{N}^{18}\text{O}$

To determine the quantities of $^{45}\text{N}_2\text{O}$ and $^{46}\text{N}_2\text{O}$ for each sample, the measured 45/44 and 46/44 ratios are first normalized to AIR for N and VSMOW for O:

- (3) $\delta^{15}\text{N}_{\text{sample}} = (^{15}\text{R}_{\text{sample}}/^{15}\text{R}_{\text{air}} - 1) \times 1000$
- (4) $\delta^{18}\text{O}_{\text{sample}} = (^{18}\text{R}_{\text{sample}}/^{18}\text{R}_{\text{VSMOW}} - 1) \times 1000$
- (5) $^{15}\text{R} = [^{15}\text{N}]/[^{14}\text{N}]$
- (6) $^{18}\text{R} = [^{18}\text{O}]/[^{16}\text{O}]$
- (7) $^{17}\text{R} = [^{17}\text{O}]/[^{16}\text{O}]$, and $^{17}\text{R} = [(^{18}\text{R}/0.0020052)^{0.516}] \times 0.0003799$

where 0.0020052 is the R value for ^{18}O in VSMOW and 0.0003799 is the mass dependent relationship between ^{17}O and ^{18}O (Sharp, 2017).

Because there are 2 N atoms in N_2O , these isotopic ratios can then be substituted into:

- (8) $^{45}\text{N}_2\text{O}/^{44}\text{N}_2\text{O} = 2 \times ^{15}\text{R} + ^{17}\text{R}$
- (9) $^{46}\text{N}_2\text{O}/^{44}\text{N}_2\text{O} = 2 \times ^{15}\text{R} \times ^{17}\text{R} + ^{18}\text{R} + ^{15}\text{R}^2$

$^{45}\text{N}_2\text{O}$ and $^{46}\text{N}_2\text{O}$ are finally calculated by converting the calibrated molecular ratios, R, ($^{45}\text{N}_2\text{O}/^{44}\text{N}_2\text{O}$ and $^{46}\text{N}_2\text{O}/^{44}\text{N}_2\text{O}$) to moles of $^{45}\text{N}_2\text{O}$ and $^{46}\text{N}_2\text{O}$:

- (10) $[^{45}\text{N}_2\text{O}] = [\text{N}_2\text{O}] \times [^{45}\text{N}_2\text{O}]/[^{44}\text{N}_2\text{O}] / (1 + [^{45}\text{N}_2\text{O}]/[^{44}\text{N}_2\text{O}] + [^{46}\text{N}_2\text{O}]/[^{44}\text{N}_2\text{O}])$
- (11) $[^{46}\text{N}_2\text{O}] = [\text{N}_2\text{O}] \times [^{46}\text{N}_2\text{O}]/[^{44}\text{N}_2\text{O}] / (1 + [^{45}\text{N}_2\text{O}]/[^{44}\text{N}_2\text{O}] + [^{46}\text{N}_2\text{O}]/[^{44}\text{N}_2\text{O}])$

Incorporation of tracer ^{15}N into N_2O over the course of the incubation produces an excess of mass $^{45}\text{N}_2\text{O}$ and/or $^{46}\text{N}_2\text{O}$ (calculated for each time point with Equations 10, 11). N_2O production can be calculated based on the equations for N_2O by Trimmer et al. (2016) (nmol $\text{N}_2\text{O} \text{ L}^{-1} \text{ d}^{-1}$) (Equations 12–16 below).

The underlying assumptions for each treatment (Table 1 and Figure 2) are:

- (1) $^{15}\text{NH}_4^+$ and unlabeled NO_2^- incubations: NH_4^+ oxidation (hydroxylamine oxidation) produces $^{46}\text{N}_2\text{O}$ from two labeled NH_4^+ (Equation 12) and some $^{45}\text{N}_2\text{O}$ -labeled N_2O based on a binomial distribution (Equation 13). Production of excess $^{45}\text{N}_2\text{O}$ indicates hybrid N_2O formation (see Figure 2 and Equation 14).
- (2) $^{15}\text{NO}_2^-$ and unlabeled NH_4^+ incubations: Nitrifier-denitrification and denitrification both mainly produce $^{46}\text{N}_2\text{O}$ (Equation 12). Excess $^{45}\text{N}_2\text{O}$ indicates hybrid N_2O production by archaeal nitrifiers (Equation 15) or fungi (Shoun et al., 2012).
- (3) $^{15}\text{NO}_3^-$ incubations: Only denitrification produces $^{46}\text{N}_2\text{O}$ (Equation 12).
- (12) $\text{Rate}_{\text{exogenous}} = \text{slope } ^{46}\text{N}_2\text{O} \times (\text{F})^{-2}$
- (13) $\text{p}^{45}\text{N}_2\text{O}_{\text{expected}} = \text{slope } ^{46}\text{N}_2\text{O} \times 2 \times (1-\text{F}) \times (\text{F})^{-1}$
- (14) $\text{p}^{45}\text{N}_2\text{O}_{\text{excess}} = \text{slope } ^{45}\text{N}_2\text{O} - \text{p}^{45}\text{N}_2\text{O}_{\text{expected}}$
- (15) $\text{Rate}_{\text{hybrid}} = (\text{F})^{-1} \times [\text{slope } ^{45}\text{N}_2\text{O} + 2 \times \text{slope } ^{46}\text{N}_2\text{O} \times (1-\text{F})]$
- (16) $\text{Rate}_{\text{total}} = \text{Rate}_{\text{exogenous}} + \text{Rate}_{\text{hybrid}}$

where F [$^{15}\text{N}/(^{15}\text{N} + ^{14}\text{N})$] is the fraction of ^{15}N in the substrate pool (NH_4^+ , NO_2^- , or NO_3^-), which is assumed to be constant over the incubation time. If known, uncertainties in F should be propagated to uncertainties in the rate calculations (Supplementary Material, Spreadsheet N_2OPR). Exogenous refers to the conversion of externally supplied N to N_2O . Concentrations before and after tracer addition should be measured to determine the exact addition made. The $^{45}\text{N}_2\text{O}$ that is produced estimated from the binomial distribution and the additional $^{45}\text{N}_2\text{O}$ that is produced through a hybrid N_2O production pathway can be disentangled using the above equations (Trimmer et al., 2016). The reader is referred to the calculation template in the Supplementary Material (Spreadsheet N_2OPR) for example calculations. It should be noted that the “total rate of N_2O production” and “% hybrid” calculated here refers to the rate of N_2O production and % of hybrid from a particular labeled substrate. Care should be taken in interpreting this as hybrid % of total N_2O production if there is substantial production of exogenous N_2O from other substrates, such as NO_3^- , in parallel incubations.

Waste Handling

HgCl₂ and ZnCl₂ are highly hazardous chemicals and waste should be disposed of accordingly.

Part B: Tracer Incubations for N₂O Consumption

Two main methods are used to perform ¹⁵N-N₂O incubation experiments to measure N₂O reduction rates during denitrification (**Figure 5**). These methods are referred to below as method #1 (Babbin et al., 2015; Sun et al., 2020) and method #2 (Holtappels et al., 2011). Unless specified, the steps below apply to both methods.

Supplies for Tracer Incubations for N₂O Consumption General Supplies (for Both Methods)

Chemicals/Gases

- Saturated KCl solution
- Glass bottles with ¹⁵N-N₂O tracer (Cambridge Isotope Laboratories Inc., part #NLM-1046-PK, purity > 98%)
- Saturated solution of HgCl₂ or 50% (w/v) ZnCl₂
- He and N₂ gas tanks for purging (UHP 5.0 to 4.6 grade)

Other Supplies

- MilliQ water supply
- Disposable gloves
- 12 mL Labco exetainers (Labco 12 mL exetainers, flat bottom, labeled, DW cap, #739W) in tube racks, labeled, with caps removed
- Exetainer caps, deoxygenated in anaerobic chamber or stored under He atmosphere before the sampling expedition
- Tygon tubing (approximately 1 m length) with adaptors to fit the Niskin bottle opening
- Luer-lock gas tight glass syringes [2.5 mL (Hamilton #81420) or 5 mL (Hamilton #81501)] and several needles (26G × 3/8") for KCl injection
- Fixed needle gas tight glass syringes for ¹⁵N-N₂O addition: e.g., Hamilton, sample lock: 1 mL (#81356), 500 μL (#81256), 250 μL (#81156), and 100 μL (#81056) (volume is based on desired ¹⁵N-N₂O tracer addition) and 26G × 3/8" needles
- Manifold to simultaneously purge 10–15 exetainers (12 mL). The purging rack should preferably be made using Viton tubing* (e.g., 1/16" ID × 1/8" OD, Fisher Scientific, #NC0511742) (see **Figure 6A**)
- 18G, 6" stainless steel needle* (that reaches the bottom of the bottle) for purging the liquid phase (e.g., Cadence science #9860) or 21G × 4 3/4" (B Braun #4665643) (depending on bottle size)
- Shorter outlet needle for pressure balance during purging* [e.g., BD PrecisionGlide Regular Bevel needles, e.g., 25G × 5/8" (#305122)]
- Dual stage regulators, stainless steel or brass tubing and Swagelok fittings, and mechanical flow controller (e.g., Porter, VCD-1000) for purging



- Incubator (or temperature-controlled room or container) covering the *in situ* temperature range of the samples
- O₂ probe/meter and oxygen sensor spots (Oxysense, Pyroscience, or custom-made sensor spots as in Larsen et al., 2016) for O₂ monitoring during incubations
- Paper towels
- Colored tape and Sharpies for sample labeling
- Notebook, log sheets and pens
- IRMS adapted for N₂/Ar measurements (e.g., see Charoenpong et al., 2014) and for N₂O isotope measurements [see McIlvin and Casciotti (2010)] by either manual injection (Dalsgaard et al., 2012) or using an autosampler

Additional Supplies Required for Method #1

- Glove bag (Sigma Aldrich, AtmosBag)
- 320 mL glass bottles (Wheaton, BOD Bottle, 300 mL, 227497-00G)
- Repeat pipettor and adaptor for 50 mL repeater pipette tips
- A thin tube that can be attached to the pipette tip and is long enough to reach the bottom of the 320 mL glass bottle
- Anaerobic chamber (GasPak, 150 Large Anaerobic Systems) with catalyst (BD BBL™ GasPak™ anaerobic and CO₂ indicators)
- Beaker for excess seawater

Additional Supplies Required for Method #2

- Serum borosilicate glass bottles (200 mL; note: total volume is 250 mL) with a 20 mm opening diameter (Ochs #102041; Kimble #61000G-200) or
 - Serum borosilicate glass bottles (500 mL, Wheaton #223952) with a 30 mm opening, 30 mm outer diameter (OD) gray bromobutyl septa (Wheaton, #224100-331), 30 mm OD aluminum crimp seals (Wheaton, #224197-01, and 30 mm seal crimper (Wheaton, #224357) and decapper (Wheaton, #224307)
 - Gray butyl septa (20 mm) (Wheaton #20-0025) (these septa need to be deoxygenated in anaerobic chamber or boiled for 5 min and stored under He atmosphere before the sampling expedition)
 - Aluminum crimp seals (20 mm) (Wheaton #224178-01)
 - Crimper and decrimper for 20 mm caps
 - 1 mL luer-lock syringe (BD #309628) connected to a 16G × 1" (BD #305197) needle, cut-off flange end and plunger removed (see **Figure 5**, setup #2)
- Note: In Holtappels et al. (2011), a plastic syringe is used to dispense the seawater into the exetainers. To limit the use of plastic components (potential for oxygen contamination), we recommend attaching a stainless steel luer-lock fitting to the outlet needle (16G), which is connected to a short piece of gas tight Viton tubing with a glass tube on the end (long enough to reach the bottom of an exetainer). This approach also makes dispensing the seawater into exetainers easier.
- Various size needles 21G × 4 3/4" (B Braun #4665643) and 23G × 1" (BD #305145)
 - Luer-lock syringes: BD luer-lock tip 3 mL (#309657)



Preparation Before the Sampling Expedition

Degas the Caps

Degas the caps at least 1 month in advance of the sampling expedition (see De Brabandere et al., 2012), and store the empty uncapped, labeled exetainers covered with plastic wrap in their original boxes. Caps are deoxygenated by storing them in plastic Ziploc bags (24 caps/bag) in anaerobic chambers with a catalytic O₂ scavenger, and flushed with He (or evacuated and filled with He several times). Alternatively, stoppers are stored under a He atmosphere in a gas tight bottle (flushed regularly with He).

Prepare Exetainers and Caps Before Sampling

Place the empty exetainers in test tube racks in sets of 12 tubes per treatment per depth (12 vials for standard ¹⁵N-N₂O treatment: four time points in triplicate or use 15 tubes if five time points are desired).

Prepare ¹⁵N-N₂O Tracer Before the Sampling Expedition

Dilute ¹⁵N-N₂O tracer in He to obtain the desired tracer concentration. First, at least two 250 mL glass serum bottles capped with gray butyl stoppers and aluminum seals are purged with He for 5 min at 5 PSI pressure (~500 ml min⁻¹) using 22G needles, to purge the bottle (make sure that there is He outflow from the serum bottles). Second, add the desired amount of ¹⁵N-N₂O tracer (e.g., 5 mL (50 times dilution of 99% ¹⁵N-N₂O tracer gas, Cambridge Isotope Laboratories, purity ≥ 98%) with a gas tight syringe to one serum bottle that will be used as the stock bottle. Third, based on the desired final ¹⁵N-N₂O tracer concentrations, use a fixed needle gas tight glass syringe to transfer ¹⁵N-N₂O and He gas mixture from the stock bottle to He-purged small serum bottles/vials to make several working tracer bottles (depending on the number of samples that will be collected, e.g., use one working tracer bottle per station). We recommend preparing the tracer bottles as close as possible to the sampling expedition date to minimize any leaking or contamination. Tracer concentration should be decided based on (1) the expected final concentration of the tracer in incubation exetainers, which should be within the range of N₂O concentrations at the sampling site, and (2) the volume of the tracer injected into each exetainer, which should be around 50 μL. Larger injection volumes will cause positive pressure in exetainers, and smaller injection volumes might introduce volume measurement errors.

To make sure that the tracer stock concentration is the same as the desired concentration, the tracer concentration should be measured prior to the sampling expedition. If the tracer concentration is too high for the Faraday cups of the IRMS, the tracer stock should be subsampled and diluted in He to the level that will not saturate the Faraday cups of the IRMS (typically 5% ¹⁵N). Determine the concentration of the ¹⁵N-N₂O tracer based on the peak area measured by IRMS and any dilution before the sampling expedition.

Sampling: Method #1 Only

Before sampling, place everything you need EXCEPT the 320 mL bottles in the glove bag. Do not flush the bag yet, and keep bag compressed. Put one bag of caps from the anaerobic chamber

with sufficient numbers of caps for the designed experiment inside the glove bag just before CTD-Rosette is back on deck.

Items to Go Into the Glove Bag:

- Water samples in 320 mL bottles
- 50 mL pipette (or repeat pipettor) and tips
- Note: If you are also performing denitrification and anammox experiments using the same method, make sure to label pipette and tips distinctly using color coding; e.g., one color for each tracer or carrier addition.
- A thin tube that can be attached to the pipette tips and is long enough to reach the bottom of the 320 mL glass bottle
- Exetainers in tube racks, labeled, with caps removed
- Exetainer caps from the anaerobic chamber
- Gloves
- Paper towels or sponge to handle spills
- Beaker for excess seawater

These shipboard operations are best done as a three-person team. One person performing the glove bag manipulations, another performing the He flushing and noting the times of tracer addition and purging the liquid phase and the third injecting the ¹⁵N-N₂O tracer into each exetainer. The task of tracer injection can be shared between the first two persons if only two-person team is available.

For Each Depth Fill 320 mL Round Glass Stoppered Bottles

Label distinctly the 320 mL bottles (e.g., using a color code) if you are performing denitrification and anammox experiments using the same method.

Obtain sample water by filling each 320 mL glass bottle from Niskin bottles using a Tygon tube, which is inserted all the way to the bottom of the bottle, overflow three times the bottle volume, and seal with a glass stopper (ensure no bubbles are present).

Put the bottles with seawater samples into a glove bag. Store bottles if the incubation experiment cannot be performed immediately due to other sampling tasks. Store bottles under conditions similar to *in situ* (for example ~10°C dark room if sampling from dark cold depths), it is recommended that experimental setup starts as soon as possible.

Note station location, date, cast number, depth, incubation condition, and treatment (¹⁵N-N₂O in this case) in notebook.

Aliquot Seawater Into Exetainers Inside a Glove Bag

Place all 320 mL sample bottles in the prepared glove bag, compress to remove all air (or evacuate), then fill and evacuate the glove bag three times with N₂ by pressing out the gas inside and refilling. Use the N₂ tube coming into the glove bag and flush every single open exetainer with gas before opening the 320 mL glass bottles.

Use the repeat pipettor and 50 mL pipette tips with the thin tube attached to aliquot 8 mL of seawater to appropriately labeled exetainers (15 exetainers for each treatment per depth: five time points in triplicates).

Seal vials with deoxygenated exetainer caps. When all exetainers are filled and capped, remove from glove bag for helium sparging.

Sampling: Method #2 Only

Label distinctly the 250 or 500 mL bottles (e.g., using a color code) if you are performing denitrification and anammox experiments using the same method. The size of bottle used depends on number of replicates and time points.

Fill each 250 or 500 mL serum bottles from Niskin bottles using a Tygon tube, which is inserted all the way to the bottom of the bottle, and overflow three times the bottle volume. Cap, bubble-free, with a deoxygenated gray butyl stopper and aluminum seal.

Store bottles under conditions similar to *in situ* (for example $\sim 10^{\circ}\text{C}$ dark room if sampling from dark cold depths) if the incubation experiment cannot be performed immediately due to other sampling tasks. It is recommended that experimental setup starts as soon as possible. Note station location, date, cast number, depth, incubation condition, and treatment ($^{15}\text{N-N}_2\text{O}$ in this case) in notebook.

Initially purge with He (0.4 L/min) for at least 15 min to lower the background concentration of N_2 and remove any O_2 contamination introduced during sampling. The inflow needle should reach to the bottom of the serum bottle (21G), while the vent needle (16G, large bore size needed for dispensing) only needs to reach into the top of the bottle, approximately 1 cm (the helium flow will push out some sample creating a small headspace in the bottle). The vent needle is connected to a 1 mL syringe with a cut-off flange end (plunger removed). To purge several serum bottles at once, use gas tight tubing with several glass (or Swagelok) *t*-pieces in series to split the helium flow.

Transfer seawater in to 12 mL exetainers using the 1 mL syringe with a cut-off flange end (Figure 5, setup #2). Insert a cut-off flange end syringe to the bottom of the exetainer while He gas is still flowing (the flow should be reduced to control the flow rate during dispensing to approximately 0.15 L/min) into the 250 mL serum glass bottle. Allow water to overflow at least two times the exetainer volume and close the exetainer (bubble free) with a deoxygenated cap. Repeat (e.g., use 15 tubes if five time points are desired).

Purge Exetainers With He

Method #1: (See purging manifold, Figure 6B). Turn on the manifold gas flow and bubble exetainers for 5 min at 5 PSI (flow rate = 0.5 to 1 L/min) with He.

- (i) Pierce the butyl septa with 23G $\times$ 1" needle (vent needle). Needle only needs to pierce through to the headspace, not be pushed in entirely.
- (ii) Attach the vial to a 4" cannula needle (He inflow), and push on entirely to bottom of vial.
-There should be a steady stream of bubbles in the exetainers.
- (iii) After 5 min, increase the pressure to ~ 5 PSI and pull vials off the manifold, being sure to remove the exit needle first to create positive pressure to prevent air contamination into the vial.

Method #2: If using method #2, a 2 mL He headspace is created. We recommend inserting a headspace as any trace amounts of O_2

introduced during dispensing will concentrate in the headspace (De Brabandere et al., 2012).

- (i) To create a headspace, remove 2 ml of water through the septa using a 3 ml luer-lock syringe and needle (23G $\times$ 1"), while adding helium simultaneously through a second needle (23G $\times$ 1"). The exetainers should be vigorously shaken after inserting the headspace.
- (ii) The headspace of the exetainers is then flushed with He twice for 15 s (approximately 0.5 L/min, using 23G $\times$ 1" as inflow and vent needles), shaking vigorously in between (De Brabandere et al., 2012). Manifolds can be purchased (e.g., Ochs # 192012) or produced in house, preferably in metal or glass allowing multiple exetainers to be flushed at once.

Although not always possible, it is preferable to do all these manipulations under *in situ* conditions, i.e., *in situ* temperature, and under red light (if the samples were collected from below the euphotic zone).

Tracer Addition

Add ~ 50 μL of $^{15}\text{N-N}_2\text{O}$ tracer into the liquid phase in each exetainer to visually confirm that the gas is injected, and the needle is not clogged. Note time of tracer injection, shake gently and invert vials to start the incubation at *in situ* temperature and light level.

In the tracer bottle, replace the tracer taken out with the same volume of saturated KCl solution (purged with He) to balance the pressure using a luer-lock syringe connected to a needle.

Other gases (H_2S , CH_4 , CO_2) lost during the He purge step can also be added back (either as a gas or dissolved) to reproduce as closely as possible *in situ* conditions before incubating.

Incubation

Replicate (preferably triplicate) samples per time point amended with ^{15}N tracer as well as replicate $t = 0$ controls immediately killed after ^{15}N -tracer addition should be incubated at *in situ* temperature and light level using at least three time points for up to a 48-h period.

Ideally, the concentration of O_2 in the exetainer is monitored over time during the incubation using non-invasive O_2 measurement technology, such as Oxysense (see text footnote 1) or Pyroscience (see text footnote 2). A sensor dot is attached to the bottom of a subset of exetainers prior to sampling. After injecting the tracer, the O_2 concentration is measured continuously or at discrete time points using a fiber optic pen to ensure low- O_2 conditions are maintained during the incubations.

Termination

Add 50 μL of a five times diluted saturated solution of HgCl_2 or 50% (w/v) ZnCl_2 to each vial with a 1 mL plastic syringe to arrest microbial activity. Diluting the HgCl_2 saturated solution reduces the toxicity of the hazardous wastes without any impact on sample preservation (e.g., see Bourbonnais et al., 2017; Casciotti et al., 2018). Shake the vial for 3 s to mix in the fixative. The replicate control exetainers (T_0) immediately sacrificed after adding the tracer for each treatment are used

to quantify abiotic N_2 production, if any, due to preservative addition and during storage. Note the time when the T_0 , T_1 , T_2 , T_3 , exetainers are sacrificed. Preserve at other time intervals, adjusting times depending on the activity expected for the sampled environment (shorter time intervals are preferable in higher activity settings): $T_1 = 7\text{--}9\text{ h}$, $T_2 = 15\text{--}17\text{ h}$, and $T_3 = 23\text{--}25\text{ h}$.

Preserved N_2 samples can be stored in the dark and likely keep for several months but measuring samples as soon as possible is highly recommended. Place the vials upside down in the dark—to reduce diffusion across septa. Precipitates caused by $ZnCl_2$ acts as barrier.

IRMS Analysis

Before analyzing samples on the IRMS in the home laboratory, place the samples on a reciprocal shaker ($\sim 150\text{ rpm}$) overnight to equilibrate the N_2 with the headspace. Shaking also facilitates removal of insoluble salts from the septum that can clog the autosampler needle. When analyzing samples from $^{15}N\text{-}N_2O$ incubations, a liquid N_2 cryotrap should be used to remove $^{15}N\text{-}N_2O$ to minimize interference from conversion to $^{30}N_2$ by the copper column (Dalsgaard et al., 2012).

N_2 standards should be prepared in exetainers on the day of measurement. Standard exetainers should be prepared in the same way as sample exetainers: 8 (or 10) mL of NaCl solution with salinity adjusted to match that of the sample water should be added into each exetainer. Purge the standard exetainers with He for 5 min, and then inject different volumes of unlabeled N_2 . The different amounts of N_2 injected should bracket the amount of N_2 in sample exetainers. Standards will be used to calculate the amount of N_2 in each sample exetainer. If possible, standards with different ratios of $^{30}N_2$ to $^{28}N_2$ should be used to cover the range of $m/z\ 30$ signals in the samples and test the accuracy of the measured $^{30}N_2/^{28}N_2$.

The isotopic composition and amount of N_2 are determined using a continuous flow system interfaced to the IRMS [Bulow et al., 2010; Babbin et al., 2015; also see Charoenpong et al. (2014) for more information regarding the IRMS set up for these analyses] or a membrane inlet coupled to a quadrupole mass spectrometer (Kana et al., 1994). In all cases, O_2 must be removed from the samples using a furnace containing a Cu flow path as the presence of O_2 has been shown to cause isobaric interferences in the mass spectrometer source by reaction with N_2 to create NO_x (Bender et al., 1994; Emerson et al., 1999).

If necessary, a non-labeled (i.e., at natural abundance) N_2 carrier gas might be added back into the exetainers before analysis to (1) lower the ^{15}N enrichment to be within the range that can be measured by the mass spectrometer and (2) to assure sufficient quantities of N_2 for analysis on the IRMS.

Rate Calculations

N_2O consumption rates from denitrification are calculated from the excess of $^{30}N_2$ produced during $^{15}N\text{-}N_2O$ tracer incubations according to Babbin et al. (2015). Assuming any preexisting unlabeled N_2O was removed during the experimental setup (purging steps), the fraction label is 100%, thus:

(17) $\text{Rate}_{\text{consumption}} = \text{slope}^{30}N_2$, i.e., $^{30}N_2$ (nM- N_2) changing over time (hour or day).

The concentration of $^{30}N_2$ in each sample exetainer is calculated based on the area of $^{30}N_2$ relative to the areas for standard exetainers measured during IRMS analysis.

The reader is referred to the calculation template in the **Supplementary Material** (Spreadsheet N_2OCON) for a better understanding and traceability of the given equations.

Waste Handling

$HgCl_2$ or $ZnCl_2$ are highly hazardous wastes and should be disposed of accordingly.

RESULTS

Figure 7 and **Supplementary Material** (Spreadsheet N_2OPR) show an example of the increase in masses $^{44}N_2O$, $^{45}N_2O$, and $^{46}N_2O$ over the incubation period following the addition of $^{15}N\text{-}NH_4^+$, $^{15}N\text{-}NO_2^-$, and $^{15}N\text{-}NO_3^-$. In all treatments, masses 45 and 46 increase significantly with time, whereas the increase in $^{44}N_2O$ is not always significant and depends on the overall rate. The steepness of the slope of the linear regression represents the production rate over time. The enrichment in $^{45}N_2O$ or $^{46}N_2O$ is also dependent on the fraction of labeled substrate which needs to be taken into account when calculating the overall production rates from a single tracer.

In incubations with relatively small rates (N_2O from $NH_4^+ = 0.047 \pm 0.007\text{ nM-}N_2O/d$) mass $^{44}N_2O$ is not changing significantly, while in treatments with higher rates mass 44 also increases with time [e.g., N_2O from $NO_3^- = 2.56 \pm 0.44\text{ nM/d}$, see calculation spreadsheet N_2OPR (**Supplementary Material**) for N_2O production rates]. A non-paired two-tailed t -test is performed in order to see if the slope over time is significantly different from zero. If the t -test p value is higher than 0.05 (for a significance level of 95%), the production rate is not significant. An increase in the number of replicates or time points reduces the uncertainty of such measurements and decreases the standard error for the linear regression.

It is possible that the product pools change exponentially over time and deviate from linearity, as indicated by a low R -squared for the linear regression. In longer incubations, a curvature generally indicates an artifact due to “bottle effects,” where bottle size (surface to volume ratio) or change in O_2 concentration artificially stimulate bacterial growth (Garcia-Robledo et al., 2016). We recommend only using the linear portion of the curve for rate calculation and report the most conservative rate.

N_2O consumption rates are similarly calculated (**Figure 8**). An example from Sun et al. (2020) is given in Spreadsheet N_2OCON (**Supplementary Material**).

DISCUSSION

We discuss below important considerations and recommendations for N_2O rate measurements using ^{15}N -tracer incubations, including data reporting and archiving.




FIGURE 7 | $^{44}\text{N}_2\text{O}$ (A), $^{45}\text{N}_2\text{O}$ (B), and $^{46}\text{N}_2\text{O}$ (C) masses over time for N_2O production ^{15}N -labeled incubations performed in the ETSP on R/V Meteor in June 2017 (Frey et al., 2020). The samples were taken at 220 m depth above the oxic-anoxic interface off the coast of Peru (sample S4, station 882).

Maintaining Anoxic Conditions Prior and During Incubations

Precautions are necessary during ^{15}N incubations of anoxic waters to determine N_2O production or consumption

to N_2 . One area of concern is O_2 contamination from air during sampling from Niskin bottles, which has been reported to result in an increase in dissolved O_2 of as much as $1\ \mu\text{M}$ (De Brabandere et al., 2012). If possible, it is preferable to replace




FIGURE 8 | Production of $^{30}\text{N}_2$ (nM-N $_2$) over time for N_2O consumption ^{15}N -labeled incubations performed in the ETNP on R/V Sally Ride in March and April 2018 (Sun et al., 2020). The samples were taken above the oxycline at 60 m depth (station 2, cast 34).

the headspace created in the Niskin bottle with CO_2 or N_2 while water is removed rather than simply allowing air invasion. It is also recommended to avoid plastic and rubber components wherever possible as O_2 can diffuse through or from these materials (e.g., De Brabandere et al., 2012) and stoppers should be deoxygenated and kept in an anaerobic chamber or under He atmosphere prior to incubations (see section “Stoppers”).

Water collection systems differ in their degree of oxygen contamination. Pump profiling system (PPS) allow sampling directly from the water column which minimizes O_2 contamination during sample collection (e.g., Padilla et al., 2016). Sampling from Niskin bottles introduce oxygen contamination in the sample (De Brabandere et al., 2012), thus most research groups typically purge with He to remove O_2 in incubation bottles (e.g., Holtappels et al., 2011; Kalvelage et al., 2013; Frey et al., 2020; Sun et al., 2020). Purging the liquid phase with He before the incubations alters ambient conditions and removes gases such as N_2O , CH_4 , and H_2S that are intricately linked to the N-cycle. Therefore, potential rates are obtained as is usually the case for these type of incubations due to changes in experimental conditions. If desired, these substrates should be added back after purging. Creating a headspace can also help draw dissolved O_2 into the headspace while the more soluble N_2O remains dissolved in the water sample. The non-invasive monitoring of O_2 concentrations inside the incubation bottle is strongly advised (see section “Incubation”).

Bottle Types

A range of bottle types and sizes have been used for ^{15}N denitrification incubations including, for instance, 1 or 0.5 L

amber glass bottles with Teflon stoppers containing two lengths of 1/8" tygon tubing with valves (Devol et al., 2006; Bourbonnais et al., 2012), 500 mL bags (Ward et al., 2009; Bourbonnais et al., 2012), or 12 mL exetainers (Holtappels et al., 2011; Bourbonnais et al., 2012). Tedlar® bags are typically hard to fill without bubble formation and the valves are not usually completely leak-tight. Thus, incubating in bags is discouraged. Larger serum bottles (at least 60 mL) with butyl rubber stoppers are recommended to measure N_2O production rates as N_2O produced in small volume exetainers might not be sufficient to be detected with the IRMS if rates are low.

Stoppers

Niemann et al. (2015) found that the thick black, non-halogenated butyl rubber stoppers leached high amounts of various organic compounds that have toxic effects during aerobic methane oxidation incubations. The gray bromo- and chlorobutyl stopper types tested did not seem to leach any organics. We thus recommend using these types of stoppers, but further tests investigating potential toxic effects of these stoppers during N_2O production and consumption ^{15}N -labeled incubations are required. Prior to anoxic or low O_2 incubations, exetainer caps should be stored under a He atmosphere to remove O_2 . Gray butyl rubber stoppers for serum glass bottles should be boiled for about 5 min in purified (e.g., Milli-Q) water and stored under He atmosphere to remove O_2 (De Brabandere et al., 2012).

^{15}N -Tracer Addition

Ideally, the final concentration of tracer added should be as close as possible to ambient concentrations. However, this is difficult

to achieve for oxic water-column samples where dissolved NH_4^+ and NO_2^- typically do not significantly accumulate. For denitrification incubations, additions of at least 5–20 μM of $^{15}\text{N}\text{-NO}_2^-$ or $^{15}\text{N}\text{-NO}_3^-$ tracers have been used [e.g., Devol et al. (2006); Bourbonnais et al. (2012)] in order to detect production of labeled N_2O or N_2 products when rates are low. Consequently, tracers are commonly added at concentrations of 10–100% of ambient concentrations, hence potential rates are investigated. The final tracer concentration is typically 0.5–5 μM $^{15}\text{N}\text{-NH}_4^+$ or $^{15}\text{N}\text{-NO}_2^-$ for water-column samples from oligotrophic waters (see Ji et al., 2015; Frame et al., 2017).

Choosing a Fixative

While a comprehensive comparison of different fixatives is still lacking, the use of HgCl_2 is advised. Ostrom et al. (2016) showed that ZnCl_2 or HgCl_2 acts as catalyst for abiotic N_2O production from Fe^{2+} oxidation coupled to NO_2^- reduction in anoxic environments where Fe^{2+} concentrations are relatively high (Antarctica Lake, sediment pore-waters). This should not be a concern for water-column samples because Fe^{2+} and NO_2^- concentrations are generally too low for this abiotic process to be significant. However, at the same time, there is an increasing awareness of how anthropogenic activities impact the mercury cycle and efforts are being made to reduce these emissions. In 2017, during the Minamata convention, Europe agreed to reduce the usage of Hg, including HgCl_2 . Since then, Sweden has banned HgCl_2 from research vessels and other European countries are following. There is an urgent need to find good alternatives.

Data Reporting and Archiving

We recommend submitting all relevant metadata and data to an open-source public data repository such as Pangaea³, the Biological and Chemical Oceanography Data Management Office (BCO-DMO⁴) or the Pan-European Infrastructure for Ocean and Marine Data Management (SeaDataNet⁵). Metadata should include sampling date, station and GPS site location, depth (m), ^{15}N treatment, amount of ^{15}N tracer added, bottle and headspace volume (if applicable), whether the sample was purged or not and gas used for purging the liquid phase, incubation time points, preservative used as well as *in situ* temperature, oxygen and nutrient (NO_3^- , NO_2^- , and NH_4^+) concentrations. $\delta^{15}\text{N}$ (vs. air) and $\delta^{18}\text{O}$ (vs. VSMOW) as well as calculated quantities of $[\text{}^{44}\text{N}_2\text{O}]$, $[\text{}^{45}\text{N}_2\text{O}]$, and $[\text{}^{46}\text{N}_2\text{O}]$ (in $\text{nmol N}_2\text{O L}^{-1}$ or nmol N L^{-1}) (see section “Rate Calculations”) should also be reported for each time point. N_2O production and consumption rates can be reported in $\text{nmol-N}_2\text{O}$ (or N) $\text{L}^{-1} \text{d}^{-1}$ or $\text{nmol N}_2\text{O}$ (or N) $\text{kg}^{-1} \text{d}^{-1}$ as long as the units are consistent and clearly stated. Common vocabularies should be used in all metadatabases and data formats, following guideline established by the British Oceanographic Data Centre (BODC) by means of the National Environment Research Council (NERC) Vocabulary Server (NVS2.0). For instance, the following terms

were submitted to the NERC Vocabulary Server (NVS2.0) to facilitate future data archiving and search.

N_2OPR = The production of nitrous oxide [N_2O CAS 10024-97-2] per day per unit volume of the experiment water sample by ^{15}N [^{15}N CAS 14390-96-6, CAS 68378-96-1, and CAS 31432-46-9] isotope labeled tracer addition, incubation and purge and trap measurement at the GC-IRMS.

N_2OCON = The consumption of nitrous oxide [N_2O CAS 10024-97-2] per day per unit volume of the experiment water sample by ^{15}N [^{15}N CAS 10024-97-2] isotope labeled tracer addition, incubation and purge and trap measurement at the GC-IRMS.

Any available ancillary dataset (e.g., microbiological sequences) should also be mentioned in the metadata.

CONCLUDING REMARKS

We present protocols to measure nitrous oxide production and consumption rates. This approach takes advantage of the fact that ^{15}N exists in low abundances in the natural environment. With recent advances in isotope ratio mass spectrometry, it is now possible to measure N_2O isotopes down to nanomolar concentrations and detect N_2O production rates as low as 0.001 nM/d . Measuring actual process rates is essential to understand the environmental factors controlling N_2O production and consumption in marine and freshwater environments.

While we present the different approaches currently used by experts in the field to measure N_2O transformation rates, a thorough inter-comparison of these protocols between labs, as well as across larger spatial and temporal scales is undoubtedly the next step moving forward. This will require a community effort that is beyond the scope of this manuscript.

DATA AVAILABILITY STATEMENT

Publicly available datasets were analyzed in this study. The N_2O production rate data from Frey et al. (2020) are available at: <https://doi.pangea/10.1594/PANGAEA.914948> and the N_2O consumption rate data are available as part of the **Supplementary Material** in Sun et al. (2020).

AUTHOR CONTRIBUTIONS

AB and CF took the lead in writing the manuscript. XS, AJ, and LAB substantially helped to write section 2, Part B: Tracer incubations for N_2O consumption. CF and XS provided the data presented in the results section. All authors provided critical feedback and helped write the manuscript.

FUNDING

The Lake Arrowhead workshop was organized by the Ocean Carbon and Biogeochemistry project office, which is supported

³www.pangea.de

⁴<https://www.bco-dmo.org>

⁵<https://www.seadatanet.org/>

by the US National Science Foundation (NSF, grant #1558412) and the National Aeronautics and Space Administration (grant #NNX17AB17G). This work was funded in part by support from the DOE Great Lakes Bioenergy Research Center (DOE BER Office of Science DE-SC0018409) to NO, NSF grant #1657663 to CF, AJ, and BW, and NSF grant #1927755 to AB.

ACKNOWLEDGMENTS

This manuscript is an outcome of the “Oceanic Methane and Nitrous Oxide Workshop: The present situation and future

scenarios!” at Lake Arrowhead in October 2018. We would like to thank all participants for engaging in fruitful and constructive discussions during the workshop. We would also like to thank Colette Kelly, two reviewers and guest associate editor Johannes Karstensen for their constructive comments.

SUPPLEMENTARY MATERIAL

The Supplementary Material for this article can be found online at: <https://www.frontiersin.org/articles/10.3389/fmars.2021.611937/full#supplementary-material>

REFERENCES

- Babbin, A. R., Bianchi, D., Jayakumar, A., and Ward, B. B. (2015). Rapid nitrous oxide cycling in the suboxic ocean. *Science* 348, 1127–1129. doi: 10.1126/science.aaa8380
- Bender, M. L., Tans, P. P., Ellis, J. T., Orchard, J., and Habfast, K. (1994). A high precision isotope ratio mass spectrometry method for measuring the O_2/N_2 ratio of air. *Geochim. Cosmochim. Acta* 58, 4751–4758.
- Bergsma, T. T., Ostrom, N. E., Emmons, M., and Robertson, G. P. (2001). Measuring simultaneous fluxes from soil of N_2O and N_2 in the field using the ^{15}N -gas “non-equilibrium” technique. *Environ. Sci. Technol.* 35, 4307–4312. doi: 10.1021/es010885u
- Bourbonnais, A., Juniper, S. K., Butterfield, D. A., Devol, A. H., Kuypers, M. M. M., Lavik, G., et al. (2012). Activity and abundance of denitrifying bacteria in the subsurface biosphere of diffuse hydrothermal vents of the Juan de Fuca Ridge. *Biogeosci. Dis.* 9, 4661–4678. doi: 10.5194/bg-9-4661-2012
- Bourbonnais, A., Letscher, R. T., Bange, H. W., Echevin, V., Larkum, J., Mohn, J., et al. (2017). N_2O production and consumption from stable isotopic and concentration data in the Peruvian coastal upwelling system. *Global Biogeochem. Cycles* 31, 678–698. doi: 10.1002/2016gb005567
- Braman, R. S., and Hendrix, S. A. (1989). Nanogram nitrite and nitrate determination in environmental and biological materials by vanadium (III) reduction with chemiluminescence detection. *Anal. Chem.* 61, 2715–2718. doi: 10.1021/ac00199a007
- Bulow, S. E., Rich, J. J., Naik, H. S., Pratihary, A. K., and Ward, B. B. (2010). Denitrification exceeds anammox as a nitrogen loss pathway in the Arabian Sea oxygen minimum zone. *Deep Sea Res. Part I* 57, 384–393. doi: 10.1016/j.dsr.2009.10.014
- Casciotti, K. L., Forbes, M., Vedamati, J., Peters, B. D., Martin, T. S., and Mordy, C. W. (2018). Nitrous oxide cycling in the Eastern Tropical South Pacific as inferred from isotopic and isotopomeric data. *Deep Sea Res. Part II: Top. Stud. Oceanography* 156, 155–167. doi: 10.1016/j.dsr2.2018.07.014
- Charoenpong, C. N., Bristow, L. A., and Altabet, M. A. (2014). A continuous flow isotope ratio mass spectrometry method for high precision determination of dissolved gas ratios and isotopic composition. *Limnol. Oceanography: Methods* 12, 323–337. doi: 10.4319/lom.2014.12.323
- Dalsgaard, T., Stewart, F. J., Thamdrup, B., De Brabandere, L., Revsbech, N. P., Ulloa, O., et al. (2014). Oxygen at nanomolar levels reversibly suppresses process rates and gene expression in anammox and denitrification in the oxygen minimum zone off northern Chile. *mBio* 5:e01966.
- Dalsgaard, T., Thamdrup, B., Farias, L., and Revsbech, N. P. (2012). Anammox and denitrification in the oxygen minimum zone of the eastern South Pacific. *Limnol. Oceanogr.* 57, 1331–1346. doi: 10.4319/lo.2012.57.5.1331
- De Brabandere, L., Thamdrup, B., Revsbech, N. P., and Foadi, R. (2012). A critical assessment of the occurrence and extend of oxygen contamination during anaerobic incubations utilizing commercially available vials. *J. Microbiol. Methods* 88, 147–154. doi: 10.1016/j.mimet.2011.11.001
- Devol, A. H., Uhlenhopp, A. G., Naqvi, S. W. A., Brandes, J. A., Jayakumar, D. A., Naik, H., et al. (2006). Denitrification rates and excess nitrogen gas concentrations in the Arabian Sea oxygen deficient zone. *Deep Sea Res. Part I: Oceanography Res. Papers* 53, 1533–1547. doi: 10.1016/j.dsr.2006.07.005
- Emerson, S., Stump, C., Wilbur, D., and Quay, P. (1999). Accurate measurement of O_2 , N_2 , and Ar gases in water and the solubility of N_2 . *Mar. Chem.* 64, 337–347. doi: 10.1016/s0304-4203(98)00090-5
- Frame, C. H., Lau, E., Nolan, E. J. IV, Goepfert, T. J., and Lehmann, M. F. (2017). Acidification enhances hybrid N_2O production associated with aquatic ammonia-oxidizing microorganisms. *Front. Microbiol.* 7:2104. doi: 10.3389/fmicb.2016.02104
- Frey, C., Bange, H. W., Achterberg, E. P., Jayakumar, A., Löscher, C. R., Arévalo-Martínez, D. L., et al. (2020). Regulation of nitrous oxide production in low-oxygen waters off the coast of Peru. *Biogeosciences* 17, 2263–2287. doi: 10.5194/bg-17-2263-2020
- Fuchsman, C. A., Devol, A. H., Saunders, J. K., McKay, C., and Rocap, G. (2017). Niche partitioning of the N cycling microbial community of an offshore oxygen deficient zone. *Front. Microbiol.* 8:2384. doi: 10.3389/fmicb.2017.02384
- Ganesh, S., Parris, D. J., DeLong, E. F., and Stewart, F. J. (2014). Metagenomic analysis of size-fractionated picoplankton in a marine oxygen minimum zone. *ISME J.* 8, 187–211. doi: 10.1038/ismej.2013.144
- García-Robledo, E., Borisov, S., Klimant, I., and Revsbech, N. P. (2016). Determination of respiration rates in water with sub-micromolar oxygen concentrations. *Front. Mar. Sci.* 3:244. doi: 10.3389/fmars.2016.00244
- Holtappels, M., Lavik, G., Jensen, M. M., and Kuypers, M. M. (2011). ^{15}N -labeling experiments to dissect the contributions of heterotrophic denitrification and anammox to nitrogen removal in the OMZ waters of the ocean. *Methods Enzymol.* 486, 223–251. doi: 10.1016/b978-0-12-381294-0.00010-9
- Huang, Y., Xiao, X., and Long, X. (2017). Fungal denitrification contributes significantly to N_2O production in a highly acidic tea soil. *J. Soils Sediments* 17, 1599–1606. doi: 10.1007/s11368-017-1655-y
- Ji, Q., Babbin, A. R., Jayakumar, A., Oleynek, S., and Ward, B. B. (2015). Nitrous oxide production by nitrification and denitrification in the Eastern Tropical South Pacific oxygen minimum zone. *Geophys. Res. Lett.* 42, 10–755.
- Kalvelage, T., Lavik, G., Lam, P., Contreras, S., Arteaga, L., Löscher, C. R., et al. (2013). Nitrogen cycling driven by organic matter export in the South Pacific oxygen minimum zone. *Nat. Geosci.* 6, 228–234. doi: 10.1038/ngeo1739
- Kana, T. M., Darkangelo, C., Hunt, M. D., Oldham, J. B., Bennett, G. E., and Cornwell, J. C. (1994). Membrane inlet mass spectrometer for rapid high-precision determination of N_2 , O_2 , and Ar in environmental water samples. *Anal. Chem.* 66, 4166–4170. doi: 10.1021/ac00095a009
- Kozłowski, J. A., Kits, K. D., and Stein, L. Y. (2016). Comparison of nitrogen oxide metabolism among diverse ammonia-oxidizing bacteria. *Front. Microbiol.* 7:1090. doi: 10.3389/fmicb.2016.01090
- Larsen, M., Lehner, P., Borisov, S. M., Klimant, I., Fischer, J. P., Stewart, F. J., et al. (2016). In situ quantification of ultra-low O_2 concentrations in oxygen minimum zones: application of novel optodes. *Limnol. Oceanography: Methods* 14, 784–800. doi: 10.1002/lom3.10126
- McIlvin, M. R., and Altabet, M. A. (2005). Chemical conversion of nitrate and nitrite to nitrous oxide for nitrogen and oxygen isotopic analysis in freshwater and seawater. *Anal. Chem.* 77, 5589–5595. doi: 10.1021/ac050528s
- McIlvin, M. R., and Casciotti, K. L. (2010). Fully automated system for stable isotopic analyses of dissolved nitrous oxide at natural abundance levels. *Limnol. Oceanography: Methods* 8, 54–66. doi: 10.4319/lom.2010.8.0054

- Myhre, G., Shindell, D., Breion, F.-M., Collins, W., Fuglestedt, J., Huang, J., et al. (2013). "Anthropogenic and natural radiative forcing," in *Climate Change 2013: The Physical Science Basis. Contribution of Working Group I to the Fifth Assessment Report of the Intergovernmental Panel on Climate Change*, eds T. F. Stocker, D. Qin, G.-K. Plattner, M. Tignor, S. K. Allen, J. Boschung, et al. (Cambridge: Cambridge University Press).
- Nevison, C., and Holland, E. (1997). A reexamination of the impact of anthropogenically fixed nitrogen on atmospheric N₂O and the stratospheric O₃ layer. *J. Geophys. Res.: Atmospheres* 102, 25519–25536. doi: 10.1029/97jd02391
- Nevison, C. D., Lueker, T. J., and Weiss, R. F. (2004). Quantifying the nitrous oxide source from coastal upwelling. *Global Biogeochem. Cycles* 18:GB1018 1–17.
- Niemann, H., Steinle, L., Bles, J., Busmann, I., Treude, T., Krause, S., et al. (2015). Toxic effects of lab-grade butyl rubber stoppers on aerobic methane oxidation. *Limnol. Oceanography: Methods* 13, 40–52. doi: 10.1002/lom3.10005
- Ostrom, N. E., Gandhi, H., Trubl, G., and Murray, A. E. (2016). Chemodenitrification in the cryoecosystem of Lake Vida, Victoria Valley, Antarctica. *Geobiology* 14, 575–587. doi: 10.1111/gbi.12190
- Padilla, C. C., Bristow, L. A., Sarode, N., Garcia-Robledo, E., Ramírez, E. G., Benson, C. R., et al. (2016). NC10 bacteria in marine oxygen minimum zones. *ISME J.* 10, 2067–2071. doi: 10.1038/ismej.2015.262
- Piña-Ochoa, E., Høglund, S., Geslin, E., Cedhagen, T., Revsbech, N. P., Nielsen, L. P., et al. (2010). Widespread occurrence of nitrate storage and denitrification among Foraminifera and Gromiida. *Proc. Natl. Acad. Sci. U S A.* 107, 1148–1153. doi: 10.1073/pnas.0908440107
- Prosser, J. I., Hink, L., Gubry-Rangin, C., and Nicol, G. W. (2020). Nitrous oxide production by ammonia oxidizers: physiological diversity, niche differentiation and potential mitigation strategies. *Global Change Biol.* 26, 103–118. doi: 10.1111/gcb.14877
- Ravishankara, A. R., Daniel, J. S., and Portmann, R. W. (2009). Nitrous oxide (N₂O): the dominant ozone-depleting substance emitted in the 21st century. *Science* 326, 123–125. doi: 10.1126/science.1176985
- Sharp, Z. (2017). *Principles of Stable Isotope Geochemistry*, 2nd Edn. Albuquerque: Open Educational Resources, University of New Mexico.
- Shoun, H., Fushinobu, S., Jiang, L., Kim, S. W., and Wakagi, T. (2012). Fungal denitrification and nitric oxide reductase cytochrome P450nor. *Philos. Trans. R. Soc. B: Biol. Sci.* 367, 1186–1194. doi: 10.1098/rstb.2011.0335
- Sigman, D. M., Casciotti, K. L., Andreani, M., Barford, C., Galanter, M. B. J. K., and Böhlke, J. K. (2001). A bacterial method for the nitrogen isotopic analysis of nitrate in seawater and freshwater. *Anal. Chem.* 73, 4145–4153. doi: 10.1021/ac010088e
- Stein, L. Y. (2019). Insights into the physiology of ammonia-oxidizing microorganisms. *Curr. Opin. Chem. Biol.* 49, 9–15. doi: 10.1016/j.cbpa.2018.09.003
- Stramma, L., Johnson, G. C., Sprintall, J., and Mohrholz, V. (2008). Expanding oxygen-minimum zones in the tropical oceans. *Science* 320, 655–658. doi: 10.1126/science.1153847
- Sun, X., Jayakumar, A., Tracey, J. C., Wallace, E., Kelly, C. L., Casciotti, K. L., et al. (2020). Microbial N₂O consumption in and above marine N₂O production hotspots. *ISME J.* doi: 10.1038/s41396-020-00861-2 [Epub ahead of print].
- Trimmer, M., Chronopoulou, P. M., Maanoja, S. T., Upstill-Goddard, R. C., Kitidis, V., and Purdy, K. J. (2016). Nitrous oxide as a function of oxygen and archaeal gene abundance in the North Pacific. *Nat. Commun.* 7:13451.
- Ward, B. B., Devol, A. H., Rich, J. J., Chang, B. X., Bulow, S. E., Naik, H., et al. (2009). Denitrification as the dominant nitrogen loss process in the Arabian Sea. *Nature* 461:78. doi: 10.1038/nature08276
- Weigand, M. A., Foriel, J., Barnett, B., Oleynik, S., and Sigman, D. M. (2016). Updates to instrumentation and protocols for isotopic analysis of nitrate by the denitrifier method. *Rapid Commun. Mass Spectrometry* 30, 1365–1383. doi: 10.1002/rcm.7570
- Weiss, R. F., and Price, B. A. (1980). Nitrous oxide solubility in water and seawater. *Mar. Chem.* 8, 347–359. doi: 10.1016/0304-4203(80)90024-9
- Wilson, S. T., Al-Haj, A. N., Bourbonnais, A., Frey, C., Fulweiler, R. W., Kessler, J. D., et al. (2020). Ideas and perspectives: a strategic assessment of methane and nitrous oxide measurements in the marine environment. *Biogeosciences* 17, 5809–5828.
- Wilson, S. T., Bange, H. W., Arévalo-Martínez, D. L., Barnes, J., Borges, A. V., Brown, I., et al. (2018). An intercomparison of oceanic methane and nitrous oxide measurements. *Biogeosciences* 15, 5891–5907.
- Zhu-Barker, X., Cavazos, A. R., Ostrom, N. E., Horwath, W. R., and Glass, J. B. (2015). The importance of abiotic reactions for nitrous oxide production. *Biogeochemistry* 126, 251–267. doi: 10.1007/s10533-015-0166-4

Conflict of Interest: The authors declare that the research was conducted in the absence of any commercial or financial relationships that could be construed as a potential conflict of interest.

Copyright © 2021 Bourbonnais, Frey, Sun, Bristow, Jayakumar, Ostrom, Casciotti and Ward. This is an open-access article distributed under the terms of the Creative Commons Attribution License (CC BY). The use, distribution or reproduction in other forums is permitted, provided the original author(s) and the copyright owner(s) are credited and that the original publication in this journal is cited, in accordance with accepted academic practice. No use, distribution or reproduction is permitted which does not comply with these terms.